







ICONIX CALLS HEX DECIMAL VARIABLE DESCRIPTION \$9800 38912 BL Bload SHGR image to bank (BK) Display SHGR image in bank (BK) \$9803 38915 DS \$9806 MS 38918 Read mouse \$98Ø9 38921 IC OPEN icon (DA) \$9800 38924 CH Plot character (DA) \$98ØF 38927 ST Plot string (\$SG(BV)) \$9812 38930 IR Plot inverse bar \$9815 38933 CO Enable/display SHGR cursor \$9818 CF 38936 Disable/clear SHGR cursor \$981B 38939 SO Enable SHGR graphics mode (320) SF \$981F 38942 Disable SHGR graphics mode (320) Clear the SHGR screen to color (CL) \$9821 38945 SC CI \$9824 38948 CLOSE icon \$9827 38951 PΙ PUT icon \$982A 38954 ш PULL icon (DA) \$982D 38957 CB Plot color bar (CL)

| ICONIX DATA HEX DECIMAL VARIABLE DESCRIPTION | | | | |
|--|---------|----------|--------------------------------------|--|
| HEX | DECIMAL | VARIABLE | DESCRIPTION | |
| \$9840 | 38976 | MH | Mouse horizontal coordinate value | |
| \$9842 | 38978 | MV | Mouse vertical coordinate value | |
| \$9844 | 3898Ø | MB | Mouse button status | |
| \$9845 | 38981 | HL | Mouse horizontal clamp (limit) value | |
| \$9847 | 38983 | VL | Mouse vertical clamp (limit) value | |
| \$9849 | 38985 | ZB | Bload buffer address | |
| \$984B | 38987 | BV | Bload/string variable (default SG\$) | |
| \$984D | 38989 | BK | Bload/display bank number byte | |
| \$984E | 3899Ø | DA | Data byte (universal) | |
| \$984F | 38991 | π | Top screen coordinate | |
| \$985Ø | 38992 | LL | Left screen coordinate | |
| \$9851 | 38993 | IT | Top icon location | |
| \$9852 | 38994 | IL . | Left icon location | |
| \$9853 | 38995 | IW | Icon width | |
| \$9854 | 38996 | IH | Icon height | |
| \$9855 | 38997 | IK | Icon bank number byte | |
| \$9856 | 38998 | CL | Color byte (universal) | |
| \$9857 | 38999 | VI | Top inverse/color bar location | |
| \$9858 | 39000 | н | Left inverse/color bar location | |
| \$985A | 39002 | WI | Inverse/color bar width | |
| \$985B | 39003 | HT | Inverse/color bar height | |
| | | | | |